GSP-Klausur Manual-Auszug

2016-07-19

fopen/fdopen/fileno(3)

NAME

fopen/fdopen/fileno(3)

opendir/readdir(3)

opendir/readdir(3)

fopen, fdopen, fileno - stream open functions

SYNOPSIS

#include <stdio.h>

int fileno(FILE *stream); FILE *fdopen(int fildes, const char *mode); FILE *fopen(const char * path, const char * mode);

DESCRIPTION

The **fopen** function opens the file whose name is the string pointed to by *path* and associates a stream with

The argument *mode* points to a string beginning with one of the following sequences (Additional characters may follow these sequences.):

Open text file for reading. The stream is positioned at the beginning of the file.

٦

- 7 Open for reading and writing. The stream is positioned at the beginning of the file.
- W of the file. Truncate file to zero length or create text file for writing. The stream is positioned at the beginning
- stream is positioned at the beginning of the file. Open for reading and writing. The file is created if it does not exist, otherwise it is truncated. The

w+

- positioned at the end of the file. Open for appending (writing at end of file). The file is created if it does not exist. The stream is
- Open for reading and appending (writing at end of file). The file is created if it does not exist. The stream is positioned at the end of the file.

a+

The **fdopen** function associates a stream with the existing file descriptor, *fildes*. The *mode* of the stream (one of the values "r", "r+", "w", "w+", "a", "a+") must be compatible with the mode of the file descriptor. shared memory object is undefined. dup'ed, and will be closed when the stream created by fdopen is closed. The result of applying fdopen to a indicators are cleared. Modes "w" or "w+" do not cause truncation of the file. The file descriptor is not The file position indicator of the new stream is set to that belonging to *fildes*, and the error and end-of-file

The function fileno() examines the argument stream and returns its integer descriptor.

RETURN VALUE

Upon successful completion **fopen**, **fdopen** and **freopen** return a **FILE** pointer. Otherwise, **NULL** is returned and the global variable *ermo* is set to indicate the error.

ERRORS EINVAL

The mode provided to fopen, fdopen, or freopen was invalid.

The fopen, fdopen and freopen functions may also fail and set errno for any of the errors specified for the

routine malloc(3).

The fdopen function may also fail and set errno for any of the errors specified for the routine fcntl(2). The **fopen** function may also fail and set *ermo* for any of the errors specified for the routine **open**(2).

SEE ALSO

open(2), fclose(3), fileno(3)

GSP-Klausur Manual-Auszug

2016-07-19

othre
ad_ci
'eate/
pthre
ad_e
xit(3
~

pthread_create/pthread_exit(3)

NAME

pthread_create - create a new thread / pthread_exit - terminate the calling thread

SYNOPSIS

#include <pthread.h>

(gra int pthread_create(pthread_t * *thread*, pthread_attr_t * *attr*, void * (**start_routine*)(void *), void *

void pthread_exit(void *retval);

DESCRIPTION

thread applies the function *start_routine* passing it *arg* as first argument. The new thread terminates either explicitly, by calling **pthread_exi**(3), or implicitly, by returning from the *start_routine* function. The latter case is equivalent to calling pthread_exit(3) with the result returned by start_routine as exit code. pthread_create creates a new thread of control that executes concurrently with the calling thread. The new

The *attr* argument specifies thread attributes to be applied to the new thread. See **pthread_attr_init**(3) for a complete list of thread attributes. The *attr* argument can also be **NULL**, in which case default attributes are used: the created thread is joinable (not detached) and has default (non real-time) scheduling policy.

calling thread with pthread_cleanup_push(3) are executed in reverse order (the most recently pushed han-dler is executed first). Finalization functions for thread-specific data are then called for all keys that have cution of the calling thread is stopped non-NULL values associated with them in the calling thread (see pthread_key_create(3)). Finally, exepthread_exit terminates the execution of the calling thread. All cleanup handlers that have been set for the

pthread_join(3). The *retval* argument is the return value of the thread. It can be consulted from another thread using

RETURN VALUE

On success, the identifier of the newly created thread is stored in the location pointed by the *thread* argument, and a 0 is returned. On error, a non-zero error code is returned.

The pthread_exit function never returns

ERRORS

EAGAIN not enough system resources to create a process for the new thread.

EAGAIN

more than PTHREAD_THREADS_MAX threads are already active

AUTHOR

Xavier Leroy <Xavier.Leroy@inria.fr>

SEE ALSO pthread_join(3), pthread_detach(3), pthread_attr_init(3)

GSP-Klausur Manual-Auszug

2016-07-19

,____

pthread_detach/pthread_self(3)

NAME

pthread_detach - put a running thread in the detached state / pthread_self - obtain ID of the calling thread

SYNOPSIS

#include <pthread.h>

int pthread_detach(pthread_t th);

pthread_t pthread_self(void);

DESCRIPTION

pthread_detach puts the thread *th* in the detached state. This guarantees that the memory resources con-sumed by *th* will be freed immediately when *th* terminates. However, this prevents other threads from synchronizing on the termination of th using pthread_join.

A thread can be created initially in the detached state, using the **detachstate** attribute to **pthread_create**(3). In contrast, **pthread_detach** applies to threads created in the joinable state, and which need to be put in the detached state later.

and leaves th in the joinable state. After **pthread_detach** completes, subsequent attempts to perform **pthread_join** on *th* will fail. If another thread is already joining the thread *th* at the time **pthread_detach** is called, **pthread_detach** does nothing

The pthread_self function returns the ID of the calling thread. This is the same value that is returned in *thread in the **pthread_create** call that created this thread.

RETURN VALUE

On success, 0 is returned. On error, a non-zero error code is returned.

pthread_self() always succeeds, returning the calling thread's ID.

ERRORS for pthread_detach

ESRCH No thread could be found corresponding to that specified by th

EINVAL

the thread th is already in the detached state

AUTHOR Xavier Leroy <Xavier.Leroy@inria.fr>

SEE ALSO

pthread_create(3), pthread_join(3), pthread_attr_setdetachstate(3).

GSP-Klausur Manual-Auszug

2016-07-19

,**__**

printf(3)

printf(3)

printf(3)

NAME

printf, fprintf, sprintf, snprintf, vprintf, vfprintf, vsprintf, vsnprintf - formatted output conversion

SYNOPSIS

#include <stdio.h>

int snprintf(char *str, size_t size, const char *format, ...); int sprintf(char *str, const char *format, ...); int fprintf(FILE *stream, const char *format, ...); int printf(const char * format, ...);

DESCRIPTION The functions in the **printf**() family produce output according to a *format* as described below. The func-tions **printf**() and **vprintf**() write output to *stdout*, the standard output stream; **fprintf**() and **vfprintf**() acter string str. write output to the given output stream; sprintf(), snprintf(), vsprintf() and vsnprintf() write to the char-

str. The functions **snprintf**() and **vsnprintf**() write at most *size* bytes (including the trailing null byte ($\langle 0 \rangle$)) to

fprintf(), sprintf(), snprintf(), respectively, except that they are called with a va_{-list} instead of a variable number of arguments. These functions do not call the va_{-end} macro. Because they invoke the va_{-arg} macro, the value of ap is undefined after the call. See stdarg(3). The functions **vprintf()**, **vfprintf()**, **vsprintf()**, **vsnprintf()** are equivalent to the functions **printf()**

output. arguments (or arguments accessed via the variable-length argument facilities of stdarg(3)) are converted for These eight functions write the output under the control of a *format* string that specifies how subsequent

Return value

\0' used to end output to strings). Upon successful return, these functions return the number of characters printed (not including the trailing

a return value of size or more means that the output was truncated. (See also below under NOTES.) the trailing '\0') which would have been written to the final string if enough space had been available. Thus, the output was truncated due to this limit then the return value is the number of characters (not including The functions **snprintf()** and **vsnprintf()** do not write more than size bytes (including the trailing 0). If

If an output error is encountered, a negative value is returned

Format of the format string

arguments. Each conversion specification is introduced by the character %, and ends with a conversion optional precision and an optional length modifier. specifier. In between there may be (in this order) zero or more flags, an optional minimum field width, an the output stream; and conversion specifications, each of which results in fetching zero or more subsequent string is composed of zero or more directives: ordinary characters (not %), which are copied unchanged to The format string is a character string, beginning and ending in its initial shift state, if any. The format

argument (and it is an error if insufficiently many arguments are given). One can also specify explicitly which argument is taken, at each place where an argument is required, by writing "%m\$" instead of '%' and "*m\$" instead of '*, where the decimal integer m denotes the position in the argument list of the desired The arguments must correspond properly (after type promotion) with the conversion specifier. By default, the arguments are used in the order given, where each '* and each conversion specifier asks for the next argument, indexed starting from 1. Thus,

printf("%*d", width, num);

GSP-Klausur Manual-Auszug

2016-07-19

and

printf("%2\$*1\$d", width, num);

must also be specified somewhere in the format string. in the numbers of arguments specified using \$; for example, if arguments 1 and 3 are specified, argument 2 are equivalent. The second style allows repeated references to the same argument. The C99 standard does not include the style using \$\$, which comes from the Single Unix Specification. If the style using \$\$ is ments, but it may be mixed with "%%" formats which do not consume an argument. There may be no gaps used, it must be used throughout for all conversions taking an argument and all width and precision argu-

For some numeric conversions a radix character ("decimal point") or thousands' grouping character is used. The actual character used depends on the LC_NUMERIC part of the locale. The POSIX locale uses ': as radix character, and does not have a grouping character. Thus,

printf("%'.2f", 1234567.89);

the da_DK locale. results in "1234567.89" in the POSIX locale, in "1234567,89" in the nl_NL locale, and in "1.234.567,89" in

The conversion specifier

A character that specifies the type of conversion to be applied. An example for a conversion specifier is:

(\0); if a precision is specified, no more than the number specified are written. If a precision is string). Characters from the array are written up to (but not including) a terminating null byte the array, the array must contain a terminating null byte. given, no null byte need be present; if the precision is not specified, or is greater than the size of The const char * argument is expected to be a pointer to an array of character type (pointer to a

SEE ALSO

printf(1), asprintf(3), dprintf(3), scanf(3), setlocale(3), wcrtomb(3), wprintf(3), locale(5)

COLOPHON

tion about reporting bugs, can be found at http://www.kernel.org/doc/man-pages/. This page is part of release 3.05 of the Linux man-pages project. A description of the project, and informa-

GSP-Klausur Manual-Auszug

2016-07-19

N

5
=
- î. ŝ
\sim

stat(2)

stat(2)

stat(2)

														DESCR		Fea		SYNOP	NAME
The <i>st_blksize</i> field gives the "preferred" blocksize for efficient file system I/O. (Writing to a file in smaller chunks may cause an inefficient read-modify-rewrite.)	The st_blocks field indicates the number of blocks allocated to the file, 512-byte units. (This may be smaller than $st_st_e/512$ when the file has holes.)	The st_size field gives the size of the file (if it is a regular file or a symbolic link) in bytes. The size of a symlink is the length of the pathname it contains, without a trailing null byte.	The st_rdev field describes the device that this file (inode) represents.	The st_dev field describes the device on which this file resides.	<pre>time_t st_mtime; /* time of last modification */ time_t st_ctime; /* time of last status change */ };</pre>	blksize_ts_blksize; /* blocksize for file system I/O */ blksize_ts_blksize; /* number of blocks allocated */ time_t_st_atime; /* time of last access */	gid_t st_gid; /* group ID of owner */ dev_t st_rdev; /* device ID (if special file) */ off t st size: /* total size in batese */	ninoe_1 sinioe; / piorecuoi */ niink_t sniink; */ uid_t suid; //* user ID of owner */	dev_t st_dev; /* ID of device containing file */ ino_t st_ino; /* inode number */	All of these system calls return a <i>stat</i> structure, which contains the following fields: struct stat {	fstat() is identical to stat(), except that the file to be stat-ed is specified by the file descriptor fd.	Istat () is identical to stat (), except that if <i>path</i> is a symbolic link, then the link itself is stat-ed, not the file that it refers to.	stat() stats the file pointed to by path and fills in buf.	IPTION These functions return information about a file. No permissions are required on the file itself, but — in the case of stat () and lstat () — execute (search) permission is required on all of the directories in <i>path</i> that lead to the file.	lstat(): _BSD_SOURCE _XOPEN_SOURCE >= 500	ture Test Macro Requirements for glibc (see feature_test_macros(7)):	int stat(const char * <i>path</i> , struct stat * <i>buf</i>); int fstat(int <i>fd</i> , struct stat * <i>buf</i>); int istat(const char * <i>path</i> , struct stat * <i>buf</i>);	SIS #include <sys types.h=""> #include <sys stat.h=""> #include <unistd.h></unistd.h></sys></sys>	stat, fstat, lstat – get file status

	SEE ALSO access(2), chmod(2), chown(2), fstatat(2), readlink(2), utime(2), capabilities(7), symlink(7)	ENOTDIR A component of the path is not a directory.	ENOMEM Out of memory (i.e., kernel memory).	ENOENT A component of the path <i>path</i> does not exist, or the path is an empty string.	ENAMETOOLONG File name too long.	ELOOP Too many symbolic links encountered while traversing the path.	EFAULT Bad address.	fd is bad.	EBADF	ERRORS EACCES Search permission is denied for one of the directories in the path prefix of <i>path</i> . (See also path_resolution(7).)	RETURN VALUE On success, zero is returned. On error, -1 is returned, and <i>errno</i> is set appropriately.	S_ISSOCK(m) socket? (Not in POSIX.1-1996.)	S_ISLNK (m) symbolic link? (Not in POSIX.1-1996.)	S_ISFIFO(m) FIFO (named pipe)?	S_ISBLK(m) block device?	S_ISCHR(m) character device?	S_ISDIR(m) directory?	S_ISREG (m) is it a regular file?	The following POSIX macros are defined to check the file type using the st_mode field:	The field <i>sr_ctime</i> is changed by writing or by setting inode information (i.e., owner, group, link count, mode, etc.).	The field <i>sr_mtime</i> is changed by file modifications, for example, by mknod (2), truncate (2), utime (2) and write (2) (of more than zero bytes). Moreover, <i>sr_mtime</i> of a directory is changed by the creation or deletion of files in that directory. The <i>sr_mtime</i> field is <i>not</i> changed for changes in owner, group, hard link count, or mode.	The field st_atime is changed by file accesses, for example, by execve(2), mknod(2), pipe(2), utime(2) and read(2) (of more than zero bytes). Other routines, like mmap(2), may or may not update st_atime .	Not all of the Linux file systems implement all of the time fields. Some file system types allow mounting in such a way that file accesses do not cause an update of the s_{1} -atime field. (See "noatime" in mount (8).)
--	---	---	---	--	-------------------------------------	---	------------------------	------------	-------	--	---	--	--	--------------------------------	--------------------------	------------------------------	-----------------------	--	--	---	--	--	---

GSP-Klausur Manual-Auszug

2016-07-19

1